



**NISS  
NETWORK AND INTERNET SECURITY  
SOFTWARE**

**MANUAL**

#### .... A MESSAGE FROM



Today's system designers are faced with tomorrow's problems. DATA COMMUNICATION is one of the important subject need to teach while learning electronics

Whether fiber optic system are for transmitting voice, video & audio or training regardless of application, it is our vision to provide you with the product you need, ensuring lasting reliability & quality.

#### OUR MOTTO;

- light years ahead – refers to leadership.

As leaders in our industry in India, we are totally committed to servicing as the standard against which all are measured in the areas of

• Design • Quality • Value • Delivery • Support.

We are truly light years ahead of our competition in this area. That means that you our valued customers are guaranteed satisfaction.

As you will move through this manual you will quickly discover that we have complete, truly innovative & superior training products. We are so committed to quality that we back our products with a complete comprehensive warranty.



AKADEMIKA LAB SOLUTIONS  
Kruti Industrial Estate, Unit no.9  
Karve Road, Kothrude, Pune-411038

+91 7447438443/+91 9004904462

[lab@akademika.in](mailto:lab@akademika.in)

[www.akademika.in](http://www.akademika.in)

## **LICENSE**

Upon your acceptance AKADEMIKA LAB SOLUTIONS grants you a non-exclusive, non-transferable, time limited licence ("**the End-User Licence**") to use the Akademika Products and any additional modules supplied to you by Akademika or its authorised Distributors (together "**the Software**") subject to the terms and conditions of this Licence.

### **FEES**

The fees payable in respect of this Licence are included in the fees payable by you to AKADEMIKA LAB SOLUTIONS authorised Distributors in respect of the Software.

### **Scope Of Licence**

Use of the NISS Software

- You may install the Software only on the specific number of computers as specified by your Licence Pack.
- The Software may only be installed on the specified number of computer systems for the purpose of your own business. Use by your associates or group companies requires a separate licence.
- We will give you an activation code to enable you to utilise the Software for the duration of the support agreement.
- The end-user must note that the Software is only functional with a valid activation code, which is unique and non-transferable. The activation code only permits the end-user to use the Software during the period specified by the annual support contract, representing a time-limited licence unless otherwise agreed with Akademika prior to or after the date of Software purchase
- The reissue of activation codes is only possible for subsequent periods where a support contract has been purchased or renewed unless otherwise agreed with Akademika prior to or after the date of Software purchase.
- You may transfer the Software to another computer provided that it is removed from the computer from which it is transferred. The Software may only be used to support the number of computers that you are entitled to based on the number of computers permitted by the Licence Packs in your possession, which increase the number of permitted computers. Any attempt to defeat or circumvent these software-enforced or un-enforced limitations is a breach of this Licence.



# **INSTALLATION GUIDE**

## Table of Contents

|    |                             |    |
|----|-----------------------------|----|
| 1. | INTRODUCTION .....          | 01 |
| 2. | SYSTEM REQUIREMENT.....     | 06 |
| 3. | SOFTWARE INSTALLATION ..... | 10 |
| 4. | DATABASE BACKUP.....        | 42 |

## **INTRODUCTION**

NISS Network and Internet Security Software helps understand the concepts behind securities involved in local network and around internet. NISS can perform hacking and tracking activities on any computer network.

The software works in server - client configuration. All the administrative work is carried out on the server computer and all the client computers work with resources provided by the server. The administrator can assign tasks to the user accordingly.

NISS explains various methods of hacking and tracking activities. Students can learn theory with the help of animations and perform an exercise for complete understanding of each topic.

- Theory topics are explained with the help of animation and simulation
- PC/Network Identification
- Cryptography (Encryption/Decryption)
- Stagenography
- Firewall
- Virtual Private Network
- Authentication Protocols
- Cryptography algorithms
  - a) Symmetric-Key Algorithms
  - b) Public-Key Algorithms
  - c) Digital Signature
  - d) Hashing Function
- Web services using Crypto techniques
  - a) Management of Public Keys
  - b) Stagenography
  - c) Communication Security
  - d) Authentication Protocols
  - e) Web Security
  - f) E-Mail Security
- Simulated operation of Hacking and Tracking activities
  - a) Hacking via HTTP
  - b) Hacking via FTP
  - c) Hacking via Phishing
  - d) Hacking via Spywares
  - e) Hacking via Virus
  - f) Hacking via Software

## **SYSTEM REQUIREMENTS**

Configuration: Pentium III or higher with at least 800MHz processor

CD ROM drive

256MB RAM

10GB free space on hard disc drive

Operating System: Windows XP

Screen resolution 1024x768 recommended

Ethernet LAN connectivity

Internet Explorer 6.0 and above.

Macromedia Flash Component

## IP CONFIGURATION

Before Running the L-SIM please make sure that,

1. IP is assigned to each PC

To test whether an IP is assigned or not to a PC,

1. Start **Command Prompt**.
2. Type "**ipconfig**" and press enter,

The following information will be there if there is an IP assigned for the PC,  
Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix :

IP Address. . . . . : 192.168.0.60 //This will be unique for the PC

Subnet Mask . . . . . : 255.255.255.0 //This should be same for all PC

Default Gateway . . . . . : 192.168.0.10 //

### **2. The Network connection is working properly,**

Check for the LAN connection icon in the system tray and detect LAN status

**Or use "ping" command**

1. Open **command prompt**.
2. Type **ping**.
3. Type **IP address** of any other PC in network and press enter.
4. Wait for the response, if it report data loss then Recheck your network connection.

### **3. If IP address is not assign, then user has to assign IP address manually, Manual IP Assignment**

1. Right click on "**My Network Places**".
2. Select icon for "**Local Area Connection**" and check its "**status**". (Connected or disconnected and Enable /Disable).
3. If it is "**Disabled**" then "**Enable**" it.
4. If status is connected then Right click on "**Local Area Connection**", and click on "**Properties**" and select "**General option**".
5. Select "**Internet Protocol**" (TCP/IP) option.
6. Select "**Properties**".
7. Select "**Use the following IP address**" option.
8. User has to enter IP address, Subnet mask and Default Gateway manually.



## SOFTWARE INSTALLATION

### Server Installation

Insert CD into CD ROM drive it will auto run with the installation screen in front of you. If CD does not run automatically you need to brows the CD and find Install.exe and run it. Following screen will appear in front of you.




To install Java click on Install Java Environment button.


Java setup will check for the system configuration and will prepare for setup




After checking it will prepare for installation




Screen below will appear




Select I accept the terms in the license agreement and click Next button.



Click Next to continue.





Select Microsoft Internet Explorer to register Java Plug-In and click Next



This will complete Java installation on your computer click Finish.

To install MySQL database click on Install MySQL button.




Click Next to continue installation



Select Typical setup type and click Next to continue installation





Click Install to continue installation



Installation progress will be shown as above.



**MySQL.com Sign Up - Setup Wizard**

**MySQL.com Sign-Up**  
Login or create a new MySQL.com account.

Please log in or select the option to create a new account.

☒ **Create a new free MySQL.com account**  
If you do not yet have a MySQL.com account, select this option and complete the following three steps.

☐ **Login to MySQL.com**  
Select this option if you already have a MySQL.com account. Please specify your login information below.

Email address:

Password:

☐ **Skip Sign-Up**

**Next >** **Cancel**

Select Create a new free MySQL.com account and click Next



**MySQL.com Sign Up - Setup Wizard**

**MySQL.com Sign-Up**  
Creating a new account.

Please enter your login information. Fields with asterisk (\*) are required.

Email Address:\*

Password:\*

Password (again):\*

**< Back** **Next >** **Cancel**

Enter Valid e-mail address and password and click Next



The screenshot shows the 'MySQL.com Sign Up - Setup Wizard' window. The title bar is blue with the text 'MySQL.com Sign Up - Setup Wizard' and a close button. The window has a light beige background. At the top, it says 'MySQL.com Sign-Up' and 'Creating a new account.' Below this, it says 'Please enter your login information. Fields with asterisk (\*) are required.' There are three input fields: 'Email Address:\*' with the value 'root', 'Password:\*' with '\*\*\*\*', and 'Password (again):\*' with '\*\*\*\*'. A red error message is displayed below the fields: 'The information entered is not a valid email address.' At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.

If e-mail address is not proper error message will get prompt



The screenshot shows the 'MySQL.com Sign Up - Setup Wizard' window. The title bar is blue with the text 'MySQL.com Sign Up - Setup Wizard' and a close button. The window has a light beige background. At the top, it says 'MySQL.com Sign-Up' and 'Creating a new account.' Below this, it says 'Please enter your login information. Fields with asterisk (\*) are required.' There are three input fields: 'Email Address:\*' with the value 'support@falconindia.biz', 'Password:\*' with '\*\*\*\*', and 'Password (again):\*' with '\*\*\*\*'. At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.

Enter Valid e-mail address and password and click Next





**MySQL.com Sign Up - Setup Wizard**

**MySQL.com Sign-Up**

Creating a new account.

Please fill out these values. Fields with asterisk (\*) are required.

First Name:\* Falcon

Last Name:\* Electro

Job Function:

Company / Organization:

Primary Business Activity:

< Back   Next >   Cancel

Type first name and last name of user



**MySQL.com Sign Up - Setup Wizard**

**MySQL.com Sign-Up**

Creating a new account.

Please fill out these values. Fields with asterisk (\*) are required.

Phone:

Zip / Postal Code:\* 400060

Country:\* India

State/Province:\* Other or N/A

☐ Please contact me to discuss how MySQL fits into my technical environment.

☐ Please subscribe me the monthly MySQL Newsletter.

☐ Please subscribe me to receive instant MySQL Notifications for important announcements.

< Back   Next >   Cancel

Type Zip code, Select Country and State and click Next



**MySQL.com Sign Up - Setup Wizard**

**MySQL.com Sign-Up**  
Creating a new account.

Please review your MySQL.com settings.

|                    |                                |
|--------------------|--------------------------------|
| Name:              | <b>Falcon Electro</b>          |
| Email Address:     | <b>support@falconindia.biz</b> |
| -----              |                                |
| Job Function:      |                                |
| Company / Org.:    |                                |
| Business Activity: |                                |
| -----              |                                |
| Phone:             |                                |
| ZIP / Postal Code: | <b>400060</b>                  |
| Country:           | <b>Other or N/A</b>            |
| State / Province:  | <b>India</b>                   |
| -----              |                                |
| Contact me:        | <b>NO</b>                      |
| Newsletter:        | <b>NO</b>                      |
| Notifications:     | <b>NO</b>                      |

< Back   Next >   Cancel

Verify entered details and click Next



**MySQL Server 5.0 - Setup Wizard**

**Wizard Completed**

Setup has finished installing MySQL Server 5.0. Click Finish to exit the wizard.

☒ **Configure the MySQL Server now**  
Use this option to generate an optimized MySQL config file, setup a Windows service running on a dedicated port and to set the password for the root account.


MySQL

< Back   Finish   Cancel


Select Configure MySQL Server and click Finish



Click Next to start configuration



Select Detailed Configuration and click Next




Select Development Machine and click Next




Select Multifunctional Database and click Next






Select Path and click Next



Select Decision Support (DSS)/OLAP and click Next



Click Next




Select Standard Character Set and click Next




Select Install As Windows Service and click Next



Select Modify Security Settings, type password and click Next




Click Execute







If above error prompt appears click Skip button and Run Configuration Wizard from Start menu this error appears when MySQL is uninstalled and reinstallation is tried. In this re-run old password will be asked if you do not remember old password simply delete MySQL folder from C:\Program Files and run MySQL setup.




Click Finish to complete installation process.


To install Tomcat Server click Install Tomcat Server button




Click Next to continue installation




Click I Agree button




Select Normal and click Next Button




Click Next button




Specify user name and password and click Next button




Brows for Java JRE folder path



Select path and click Install button









Click Finish to complete Installation

To install File Zilla Server click on Install File Zilla Server button




Click I Agree button







Select Standard and click Next button





Click Next button



Click Next button




Select Start manually and click Install button




Click Close button to complete installation



Type password and click OK button



After successful login above screen will appear



After logged out above screen will appear

To install NISS application click Install NIST button




Click OK button to continue



Click Next button to continue





**Network and Internet Security Trainer Setup**

**Customer Information**

Please enter your customer information

User Name:  
Dinesh


Organization:  
Falcon

Serial Number:  
123 - 456

Advanced Installer

< Back Next > Cancel

Type User Name and Organization Provide Serial Number and Click Next button



**Network and Internet Security Trainer Setup**

**Select Installation Folder**

This is the folder where Network and Internet Security Trainer will be install...

To install in this folder, click "Next". To install to a different folder, enter it below or click "Browse".

Folder:  
C:\Program Files\Apache Software Foundation\Tomcat 5.5\webapps


Browse...

Advanced Installer


< Back Next > Cancel

Select following path from Browse C:\Program Files\Apache Software Foundation\Tomcat 5.5\webapps\ and Click OK and Click Next button





Click Install button to start installation






Click Finish button to complete setup.**Database Backup**

Copy NISTBackup.sql file from The Database Folder available in the CD and past it to C:\Program Files\MySQL\MySQL Server 5.0\bin directory.


After successful installation open MYSQL prompt. Path for accessing the same:  
Start->Programs->MySQL->MySQL Server 5.0 ->MYSQL Command Line Client.




Once the Installation is complete we have to click on My SQL Command line client then enter the password "root".


Then on the Mysql> command line  
**create database niss;**

Now to check if this Data Base is created type on the Mysql Command Line  
**show databases;**




It will display the following details- Now type show databases;





Now on the MySQL Command line type  
**mysql> mysql -u root -proot NISS < NISTBackup.sql**



- 1) Now open internet explorer and type on the address bar as <http://localhost:8080/NISS/> to create User Id.
- 2) For admin login <http://localhost:8080/NISS/Admin/FrmAdminLogin.html>  
 User Name: admin and Password: a.  
 Here we will be defining the Users as hacker or tracker
- 3) Refer the User Manual to work with the software.